

Stopwatch Plus - User guide



Stopwatch Plus is a time measuring software tool. It contains a **Counter-up**, **Counter-down** and a **Reminder**. From the main menu, select the desired option using the joystick or use the **Options->Open** command.

➤ Counter-up

- Press **Start** to start counting.
- Press **Store** to store the current time stamp or press **Stop** to stop the counter.
- Press **Reset** to reset the counter.
- Press **Back** to go back to the main menu.

The **Counter-up** has a precision of centiseconds (1/100 of a second). The maximum time for counting is 99 hours.


➤ Counter-down and Reminder

When you select and open the **Counter-down** or the **Reminder**, you are required to enter the settings for the selected option.

When the settings page is shown, select the **Options->Change** command from the left soft key or press the joystick to change the current selected setting value. Press the **Options->Continue** command to show the **Counter-down** or the **Reminder** page. Press **Cancel** to go back to the main menu.

In the settings page you can set or change the following values:

- **Period** (hh:mm:ss). Enter the time period to be counted-down or to use as the reminder time. The maximum value is 23 hours, 59 minutes, 59 seconds. The minimum value is 15 seconds.
- **Alert text**. Enter the text to be shown when the time period has elapsed. The text will blink.
- **Play sound**. If set on **Yes**, a sound will be played when the time elapses.
- **Sound file**. Select the sound file to be played when the time elapses. Available only if the **Play sound** setting is set on **Yes**.
- **Sound volume**. Set the volume of the sound. The value is in percents (%). Available only if the **Play sound** setting is set on **Yes**.
- **Vibrate**. If set on **Yes**, the phone will vibrate when the time period elapses. The phone will not vibrate if in the settings of the current profile the **Vibra alert** setting is set **Off**, even this option is set on **Yes**.
- **Backlight**. If this setting is set on **Always on**, the backlight of the main screen will be kept active as long as the **Counter-down** or the **Reminder** page is shown, even the counter has not been started. The keypad is also unlocked. Some phones will also keep the backlight of the keypad active.



Counter-down

When the **Counter-down** page is shown:

- Press **Start** to start the counting-down.
- During the counting-down, press **Restart** to restart the counter.
- Press **Stop** to stop the counting-down. Press **Continue** to continue the counting-down or press **Reset** to reset the counter.

- When the time elapses, press **Reset** to reset the counter.
- Press **Back** to go back to the settings page.

When the time elapses, the alert text will be shown in blinking mode, the sound will be played and the vibra will be started if these were enabled in the settings page. The sound and vibra will be active for 90 seconds and will be repeated 3 times at an interval of 2 minutes; afterthat the sound and vibra will not anymore be activated. The alert text will blink until you press **Reset** or **Back**.

Reminder

When the **Reminder** page is shown:

- Press **Start** to start the counting-down.
- During the counting-down, press **Restart** to restart the counter.
- Press **Stop** to stop the counting-down. Press **Continue** to continue the counting-down or press **Reset** to reset the counter.
- When the time elapses, press **Reset** to reset the counter.
- Press **Back** to go back to the settings page.

When the time elapses, the alert text will be shown in blinking mode, the sound will be played and the vibra will be started if these were enabled in the settings page. After 90 seconds since the time has elapsed the sound and vibra will be stopped and the counter is automatically restarted. The cycle is repeated until you press **Restart**, **Reset** or **Back**. The reminder page shows you also the missed sound and vibra notifications after the time has elapsed.



Write for support to: Tektronic Srl, contact@tektronic.ro, <http://www.tektronic.ro>